


PxrAttribute

PxrAttribute allows the user to read attributes attached to (stored) on a node. Such an example would be to add a color attribute to a set of objects to be read by a material later. In this way, a material can change its result based on the object being rendered instead of a different material. Below there are color attributes attached to the sphere's of the shader ball. A single [PxrSurface](#) material renders with a different diffuse color as specific by each shape's defined attribute. Examples on usage are below.



There may be a performance penalty for using this node in many places in your scene. Efficiency is key to avoid too many evaluations of user attributes if not necessary.

Input Parameters

Variable name

This field takes a string that identifies the attribute. The string should include the namespace for the attribute and the attribute name separated by a colon. For example, trace:maxdiffusedepth or user:Ball.

Variable Type

This specifies the type of variable to read and must match what was specified above on the other nodes.

- Integer
- Float
- Float 2
- Color
- Point
- Vector
- Normal

Output Parameters

resultF

A float result.

resultRGB

The color result.

Example Usage

DCC applications may use a different mechanism for applying a user attribute. Below are two examples for applying a color user attribute named "Ball" to a shape:

Maya:

Add a Pre Shape MEL attribute to the shape using the Attributes > RenderMan menu

```
RiAttribute "user" "color Ball" 1 0.2 0.65
```

Katana:

The below is an OpScript example of the same attribute in Katana

```
gb = GroupBuilder()
gb:set("value", FloatAttribute({1.0, 0.2, 0.65}, 3))
gb:set("type", StringAttribute("color"))
Interface.SetAttr("prmanStatements.attributes.user.Ball", gb:build())
```

Houdini:

See [Using PxrMaterialID](#) as an example of how to add user attribute in Houdini.