# The ROP Node

- Standard Controls
  - o Buttons
  - Common Choices
- Rendering
   Sampling Tab
  - Shading
  - Render
  - o Dicing
  - Statistics
  - Advanced

Rendering in RenderMan is accomplished using the ROP node in Houdini. If you choose the shelf button, we will create and connect the common choices for rendering including using the PxrPathTracer Integrator.


There are many options for rendering and some are obscure or for special circumstances. We support having multiple ROP nodes in Houdini so that you can tailor each one to your task, be it IPR settings, different display drivers for render passes, or useful changes you'd like to see as you render. Be sure to use the render controls of the ROP node you are wishing to view the results from. As an example, you could create a ROP node with settings designed for fast IPR and another for final production renders.


This document aims to help you navigate the differences as simply as possible.



For information on providing AOVs and LPE content for compositing, see the page on AOVs

Information on the Driver Tab and rendering to a device can be found here.





#### Standard Controls

## **Buttons**

- Render: Initiate an Interactive Render to RenderMan
- Stop: Cancel or End the interactive render (you may also stop the render from "it")
- Render in Background: Render while keeping the Houdini UI available
- Dump Rib: Export a RIB file (defaults to the location of your .hip scene file) The default is Binary to save space. You may change this in the RIB Tab
- Bake: Run a bake render to bake pattern networks
- Controls...: Additional options for rendering like quality overrides and frame settings

## **Common Choices**

- · Valid Frame Range: Choose the frames to render, not valid for interactive rendering
  - Start/End/Inc: The frame range and increments, accepts floating point values
- Render With Take: Which versioning to use
- · Camera: Path to the chosen camera from which to render. This must have a camera specified. If using our shelf button, we will populate the field
- · Override Camera Resolution: Change the render resolution from the one specified in the camera settings

# Rendering

- Integrator: What integrator to use. If this is empty or not set, we use the PxrDefault Integrator
- Enable Depth of Field: Allows the use of Depth of Field settings, this is an easy on/off setting should you want to disable it for scene tweaking
- Allow Motion Blur: Turns on motion blur for scene entities. Please note the motion blur of volumes is controlled by the BxDF, PxrVolume separat
  ely


# **Sampling Tab**

See also Renderer Options for more details

- Pixel Variance: This is your main quality control for the render. Lower values are higher quality. Typical production settings are 0.005 to 0.001 (extreme high quality). 0.01 is reasonable good to medium quality depending on scene complexity
- Sampling

- Minimum Samples: The lowest number of sample required per-pixel. A value of 0 takes the nearest square root of the Maximum Samples setting. Higher numbers may be necessary to capture small image features like small particles or thin hair
- Extra Minimum Samples: If a pixel fails the variance test, this value forces a specified number of additional samples before testing the variance again. At 0 it defaults to the same number as the Minimum Samples
- Maximum Samples: The most samples we will take before stopping samples on a pixel. Higher values may be necessary when
  rendering depth of field, motion blur, or other noisy effects
- o Dark Falloff: If an area of the image is darker than this threshold, stop sampling since it won't be visible or perceived
- Adapt All: Test all the AOVs against the variance threshold. This means your AOVs are more likely to be noise-free but can significantly
  increase render times as some AOVs may trigger more samples without much gain to image quality
- Incremental: Render frame passes instead of bucket/tile based rendering. Preferred for most rendering choices including batched and checkpoint
  ed renders
- Pixel Filter Mode
  - Weighted: This is the default setting where samples are filtered together
  - o Importance: This is required for denoising applications (Hyperion or Nvidia) where pixels are independent of one another
- Sample Offset: This allows several images to be rendered in parallel (with different sampleoffset values) and then combined
- Extreme Motion/DOF: Changed the sampling technique when depth of field or motion blur is extreme/dominant in the image. This is more accurate but introduces some overhead

## Shading




See also Renderer Options for more details

#### Trace

- World Origin: Allows the user to select the origin fr the scene, useful for very large scenes where precision issues may cause slow renders or artifacts in raytracing
  - Camera: The default uses the render camera position as the world origin (0, 0, 0)
  - World: The original default where your scene grid is used as the origin for your scene
  - World Offset: User supplied coordinates as the new origin for the scene during rendering
- World Offset: The user defined location of the new scene origin if World Offset is chosen above

• Light Learning Scheme: This option allows the renderer to use light attributes and positions/occlusion to inform the renderer of how to balance samples across the scene to improve convergence. Complex scenes benefit more than simple scenes or scenes with few lights

## Render



See also Renderer Options for more details

- · Checkpoint Render: Batch render a scene while incrementally leaving checkpoint files for viewing or restarting later
- Search Paths: These point to locations where RenderMan should look for custom plugins, image directories, and more
  - O Shader Path: Path to find shader plugins
  - Texture Path: Path to search for texture files

- o Display Path: Path to find Display plugins
- o Archive Path: Path for finding and loading delayed read archives/RIB
- o Procedural Path: Path to find procedural plugins (like Maya's Xgen)
- O Rix Plugin Path: Path to other RenderMan plugins
- Directory Map: Path remapping
   Limits: These define memory limits for certain features of the renderer. On modern machines you may have enough memory to hold most entities in RAM, but for some parts of the render you may be able to efficiently reduce the memory used to render large scenes (geometry must be in-memory) We attempt to set this at reasonable limits by default. For more information, look under Configuration

## **Dicing**

See also Renderer Options for more details


- Minimum Width: Minimum pixel width to render hair/fur/curves. A small amount may improve anti-aliasing of fine curves
- · Offscreen Multiplier: The multiplier of the dicing rate for objects offscreen that may appear to have poor shape in reflections or cast shadows that are from obviously under-diced objects

## **Statistics**

See also Renderer Options for more details

- Debug: Allow shading debug messages
- Render Statistics: Output render stats on render completion

## **Advanced**



### See also Renderer Options for more details

- LPE: This section defines lobes for output to LPE, this includes the lobes from PxrSurface and PxrMarschnerHair. Custom materials may also define lobes for output here as User lobes. Note that the 1 position for each set, Diffuse, Specular, and User is empty as a fall through
- Bucket Order: Render bucket order. Supported values: horizontal, vertical, zigzag-x, zigzag-y, spacefill, random, spiral, circle
- Order Origin: Specify the first bucket/tile rendered when using Spiral or Circle choices
- Frame Aspect: The aspect ratio of the rendered output image
- Variable Substitution: Meant for RIB file parsing only