


AOV Setup and Viewing

RenderMan for Houdini exposes a powerful system of [AOV](#) creation and light transport output called [Light Path Expressions](#). To simplify usage, many of the most common AOVs are available as presets in the ROP node under [Images](#).

Display Driver

A [Display driver](#) identifies the file output and type for your rendered image. You may also specify additional AOVs to be added to the file under "Extra Image Planes" described below. By default we supply a single driver defaulted to an OpenEXR file. You can add more using the **Displays** parameter at the top of the Images Tab



- Display - The path and the name of the file to be rendered with any appropriate tokens like \$F4 for a frame padding of 4 digits in an .exr file
- Create Intermediate Directories - This allows Houdini to create the correct structure based on the tokens you've used above
- Device - The destination of the render, inside Houdini we default to "it" as the display device but you may specify supported file formats as well as Houdini's own display
- Denoise - Denoise the channels of this driver either as a single frame or as a sequence/multi-frame

Output

- [Pixel Filter](#) - The filter used to combine samples into a finished pixel color, note that Denoise options enforce Importance Sample Filtering
- Relative Pixel Variance - This is a multiplier on the setting used for Quality of the final frame. This may cause this display driver to be sampled as the main driver of quality by changing the multiplier lower, or effectively ignored if higher than 1
- Filter Width - Increasing this value may soften the resulting image by taking in more and more samples before filtering them together for a pixel. Note that the values provided per-filter are the typical lowest default
- Remap - [Remap](#) the image to handle highlights and other color values in-render

Extra Image Planes

Presets of additional common outputs are included with options to create your own as discussed below/

Built-in AOV

Instead of specifying a variable, you can select one of the following:

Default AOVs are the beauty and alpha channels.

Standard AOVs are data AOVs used for compositing operations that need a data driven pass like normals, depth, etc.

Diagnostic provides you with data about the render stored in a channel for later

 Default

☒ Ci

☒ a

 Standard

☐ Oi

☐ Nn

☐ Ngn

☐ Non

☐ P

☐ Po

☐ PRadius

☐ Tn

☐ Vn

☐ VLen

☐ curvature

☐ du

☐ dv

☐ dw

☐ dPdu

☐ dPdv

☐ dPdw

☐ dPdtime

☐ id

☐ incidentRayRadius

☐ incidentRaySpread

☐ motionFore

☐ motionBack

☐ mpSize

☐ outsideIOR

☐ time

☐ u

☐ v


☐ w

 Diagnostic

☐ cpuTime

☐ sampleCount


Lighting passes are the typical passes used when making visual adjustments during compositing. We also provide per-lobe LPE to extract specific lighting information from Pxr materials. Note that these are additive and physically correct. Compositing operations involve addition and subtraction to retain what happens during rendering. Multiplication and division may introduce artifacts and is not recommended in post operations at the pixel level.



Shadow AOVs require that we compute the Beauty render and are used for compositing shadows onto filmed plates/footage

Mattes can help you select and isolate objects or materials in post, we recommend PxrCryptomatte for this now

Integrator AOVs are data AOVs built into the integrator being used (verify support for your chosen integrator). `__depth` is useful and is anti-aliased. Again, check the examples on the [AOVs](#) page.



Custom AOV

You may specify your own AOVs and Light Path Expressions here. This is useful for creating and storing LPE for per-light, per-object, or specific light paths you wish you capture.

To specify an AOV you should provide the following information to RenderMan:

Name - Specify the name and type of the AOV, e.g. varying normal Nn. These selections that are built in simply need you to choose them, we provide the correct name to the renderer.

Source - Set the source string (expression) for an LPE. If using a built-in LPE (see below images), you can leave this field empty; otherwise, you must provide the appropriate LPE expression, e.g. the type: **color** and expression: **lpe:C<RD>[<L.>O]**.

Filter - For color AOVs, the recommended filter is Gaussian, this typically should match the Beauty or Ci Display Channel. Data AOVs should be unfiltered.

Relative Pixel Variance - This is a multiplier on the setting used for Quality of the final frame. This may cause this display channel to be sampled as the main measure of quality by changing the multiplier lower, or effectively ignored if higher than 1

Filter Width - As above, when using color AOVs, a filter width of 2 2 using Gaussian matches the default render settings.

Statistics - This field is only used if you are specifying AOVs manually for [Denoising](#).

Remap - As explained [above](#)

The screenshot displays the 'primarySpecularLobe' material property settings in the Unreal Engine 4 Material Editor. The interface is organized into several sections:

- Disable AOV:** A checkbox that is currently unchecked.
- Name:** The material name is 'primarySpecularLobe'.
- Source:** The source is set to 'Color' with the expression `1pe:C[S2].* [<L.>0]`.
- Advanced:** This section is expanded and contains:
 - Pixel Filter:** Set to 'Gaussian'.
 - Relative Pixel Variance:** A slider set to 0.
 - Filter Width:** A slider set to 2.
 - Statistics:** Set to 'none'.
- Remap:** This section is collapsed and contains:
 - Breakpoint:** A slider set to 0.
 - Max Value:** A slider set to 0.
 - Smoothness:** A slider set to 0.