# **PxrStylizedLines**

### Visualizer

### Visualizer

Use these settings to preview certain AOVs to aid in the development of your creative linework.

#### Beauty

The Beauty AOV being rendered before the Stylized Looks filters are applied

#### **Final Lines**

View the output of the lines only.

### **Final Lines Invert**

An inverted visualization of your lines

#### Final Lines + Beauty

This is the default visualizer and combines your linework with the beauty AOV

#### **Final Lines Alpha**

The alpha generated by the lines.

#### Line Thickness from Pattern

Visualize the thickness of your lines being generated from any patterns or textures plugged into the Line Thickness Input of your PxrStylized Control node.

### Line Thickness from Lighting

Visualize the line thickness generated from the scene lighting

### **Diffuse Luminance**

The luminance of the diffuse AOV

#### **Diffuse Energy**

The energy emitted by the Diffuse AOV

### **Z** CamDist

Use this selection to visualize your CamDist

# **Light Signal AOV**

The name of a color AOV to do line detection on.

Typically this would be diffuse, but you can also put a light AOV here to determine the transition between photoreal and stylized based on the light emission. This AOV has to be set up in Maya/Katana/Houdini or DisplayFilter will exit.

# **Diffuse Energy From**

Under the hood a white shader approximation is created based off the Signal AOV to drive the Hatching. By default using average of RGB components of Signal AOV, but can also divide Signal AOV lighting results with a pure albedo from NPRalbedo AOV or albedo AOV. If NPRalbedo AOV chosen, must set Albedo Color in Stylized Controller Pattern node.

# **Light Mask Switch**

Use light aov defined in signal\_aov\_string above as mask for previously daisy-chained Stylized shaders and/or physically based lighting

### **Line Type**

aov - custom AOV defined below
outline - line on alpha of object
sections - line on random id
lineNZ - line on combination of X Y components of surface normal and Z depth, good for unit scale
curvature - line on change in surface normal
camdist - line on change in camera distance


### **Final Line Gamma**

After line detection happens, runs gamma on final lines. When using the Curvature Line Type, you can use this parameter to control the curvature falloff to fine-tune your linework

### **Weight Type**

During line detection weighting to get a variance

Different weight types graph (interactive graph https://www.desmos.com/calculator/q2pkrrwv8h):



### **Sigmoid Sharpness**

See: https://www.desmos.com/calculator/g4jbxcvtqz and modify sharpness variable "a"

#### Sigmoid Offset

See: https://www.desmos.com/calculator/g4jbxcvtqz and modify offset variable "o"

# **Activation Function**

During line detection weighting to get a variance

### **Line Thickness**

The thickness of the lines, measured in pixels

# **Dilate Sort Group**

### **Dilate Sort Switch**

When turned on: dilates the signals that contributed to the lines (albedo color, thickness, z-depth, ...) to go off the geometry, since the line detection goes off the geometry. If Dilate Sort is off, there will be an undesirable double-line corresponding to the incorrect data off geometry. Also sorts to assign higher priority to objects closer to camera.

### **Dilate Sort Radius**

The size of the radius, in pixels, to dilate the signals.

# **Dilate Depth Scale**

Scale Z depth for sorting based on scene scale

### **Dilate Sort Weight Type**

Same weight types as for Line thickness edge detection, but for Dilate Sort radius

### **Dilate Sort Use Alpha**

If the object has an alpha channel: the zero alpha on camera depth will be incorrect. Instead, switch to ON to mix between camera depth of objet and Dilate\_Sort\_Max\_depth based on alpha

### **Dilate Sort Max Depth**

Max Depth to consider for outside of alpha

### **Line Thickness Scaling Group**

### PxrStylizedControl

Multiply Line Thickness by Line Thickness values on PxrStylizedControl per object

# PxrStylizedControl Scale

Globally scale line thickness. If you have line thickness set per object and they are all different values, and you up the resolution of the render, use this global scale to increase or decrease line thickness of all lines, since they are based on pixel width

### Zdepth

Multiply Line Thickness by Z Depth

#### Cam Dist Z Min

Remap camera distance: Linear step Min on Z (blue channel from lineNZ)

#### **Cam Dist Z Max**

Remap camera distance: Linear step Max on Z (blue channel from lineNZ)

### **Z Min Thickness Scale**

At Cam Dist Z Min, scale line thickness by this amount

#### **Z Max Thickness Scale**

At Cam Dist Z Max, scale line thickness by this amount

### Lighting

Multiply Line Thickness by Lighting signal (view Line Thickness From Lighting in Visualizer dropdown to see this signal)

# **Light Min Thickness Scale**

Scale (multiply) Line Thickness by this value in shadows

### **Light Max Thickness Scale**

Scale (multiply) Line Thickness by this value in light areas

### **Light Min Max Thick Invert**

Invert min max above: so thicker in shadows

# **Light Thickness Gamma**

Apply gamma curve to light response to drive thickness

### **Line Color Group**

### **Line Color From**

Offers a number of different functions to determine line color

### **Use Line Mask**

Mult by line mask from pattern node in AOV NPRlineMask

### Lines Inside

Mult by alpha for only inside lines from line detect, don't go off geo

### **Light Response**

Color lines by lighting