

PxrNormalMap

Produces a bumped normal from a normal map (a color map encoding the normal). Bumps are applied in *object* space. The change in scale between *object* space and *current* space is automatically applied by the node.

Like the other texture nodes, this node takes a manifold which describes either a 2D or 3D domain to apply a the texture to. The default behavior if no manifold is attached, is to apply over the s,t domain defined on the geometry.

Texture atlas format files can be read in either UDIM (Mari) format or Mudbox format.

Input Parameters

Bump Scale

Scale the bump effect. Typical range is from 0.0 to 2.0.

Input Normal

Specifies normal map color (this parameter is ignored if *Filename* is provided).

Filename

Normal map filename. The shader reads only one channel of the file from the Mapping Controls' *Channel* specified below. Note that this will be read in as the Mudbox normal map format in tangent space.

Bump Overlay

Connect a [PxrBump](#) or [PxrNormalMap](#) node here if you need to combine multiple patterns.

Bump Orientation

Invert Bump

Invert the bump orientation. Concave becomes convex and vice versa.

Orientation

Some texturing applications offer different orientations, like OpenGL or DirectX. You can also go manual (choose "Custom") to try to fix your normal map's appearance.

Flip X

Flips the x axis (red channel) of the normal map. There isn't any standard to encode normal maps and every application will encode them differently. This switch, combined with *Flip Y* and *Invert Bump* will allow you to set the correct orientation.



This switch is only visible when **Orientation** is set to "Custom".

Flip Y

Flips the y axis (green channel) of the normal map. There isn't any standard to encode normal maps and every application will encode them differently. This switch, combined with *Flip X* and *Invert Bump* will allow you to set the correct orientation.



This switch is only visible when **Orientation** is set to "Custom".

Mapping Controls

Manifold

Provides the range over which to apply the texture. Defaults to s,t.

Advanced

Reverse Normal

Reverse the resulting normal.

Adjust Amount

Amount to adjust the normals when they are facing away from the camera

Surface Normal Mix

The amount to mix the resulting normals with the surface normals

Disabled

Use the geometric normal

Output Parameters

resultN

The bumped normal.

Normal Maps Orientation

Sometimes you might apply a normal map to your geometry and it will look wrong. Generally, it's an orientation problem and you will have to find the correct combination of *Invert Bump*, *Flip X*, and *Flip Y*. The best method is to start an IPR/LiveRender session and try various combinations. Once you have found the correct combination for your authoring application (ZBrush, Mudbox, 3DCoat, etc), it should be good for all maps exported from that application with the same settings.

