## **Denoiser in Blender**

RenderMan for Blender includes two different denoisers, one that is suitable for interactive work, and the other is meant for final renders.

## Interactive Rendering

For interactive renders (viewport renders, IPR to "it"), RenderMan uses Nvidia's AI Denoising solution.

Nvidia's AI denoising is not available for macOS.

For more information about using the Nvidia denoiser in "it", refer to the "AI Denoise" section in Image Tool.

For viewport renders, you can turn on the denoiser by going to the viewport preferences and putting in a check next to Use Optix Denoiser.



If you then start a viewport render, it should immediately start to denoise.



For preview renders (i.e.: hitting F12 or RenderRender Image), and you're rendering to the the Blender render window, you can also turn on the Nvidia denoiser by clicking on **Use Optix Denoiser** in the Render Properties tab.

> Grease Pencil					
🗸 💦 Rend	er				
22	Render	<b>**</b>	Render Animat	ion	
	Renderer	RIS		~	
	🔽 Default Light				
	Render Holdouts	Off		~	
	Persistent Data				
▼ Display					
	Render to		der	~	
		Us	e Optix Denoiser		
Threads Control					
	Render Threads		-2		
Batch Threads		ts	0		

You should immediately see the denoised results in the render window.



## **Batch Rendering**

For final renders, RenderMan uses the AI Denoiser from Disney Research (see Denoiser). To denoise your final renders in RenderMan for Blender, follow these simple steps, and for more detailed information on using AOVs in Blender, here is the link!

1. Go to the View Layer Properties and click Switch to RenderMan Displays

8.		Q					×
ŧΥ							
Ċi							
T							
6							
\$	Switch to RenderMan Displays						
_							
6							
2							
0/							
533							

2. In the RenderMan Display, select your beauty AOV and turn on Denoise

-			۶		~
19					
Ċi					
6					
۲					
6					
99					
535					
		Contraction of the second seco			
	🗹 Denoise				

3. Set any denoiser parameters and you're all good to go! Note : if you are rendering using Blender Batch, then you will need to turn off Use Blender Compositor.

ł۲	ko Scene	
â	Render Engine	RenderMan v
1	> 💦 Render	
	V 💦 Batch Rendering	
6	Batch Render	Batch Bake Render
S		Render Animation
_		
۲	V 💦 Spool Options	
67	Spool Style	Blender Batch v
~	Spool to	LocalQueue
1004	Frame Chunking	
83		Use Blender Compositor
	Custom Render Commands	
	▼ RIB Options	
	RIB Form	at Binary ~
	RIB Compressi	on None ~
	▼ Denoising	
	Asymmet	
	Output Directo	ry 📄
	Мо	de Single Frame v
		Flow
		Verbose



Pixel Variance = 0.26 Max Samples = 64